

MM MM MMM MMM MMMM MMM MMMM MM MM MM MM	000000 00 00 00 00	00 00 00 00	NN NN NN NN NN NN NN NN NNNN NN NN NN NN	TTTTTTTTT TTTTTTTTT TT TT TT TT TT TT T	• • • •
CCCCCCCCCCCCCCCCCCCCCCCCCCCCCCCCCCCCCC	LL LL LL LL LL LL LL LL LL LL LL	DDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDDD			

```
N 13
16-SEP-1984 16:35:56.71 Page 1
MOUNT.CLD:1
                   'V04-000'
  Version:
         V03-007 DAS0002
                                     David Solomon
                                                                 09-Jul-1984
                   Add /[NO]REBUILD.
         V03-006 HH0028
                                     Hai Huang
                                                                  27-Jun-1984
                   Make appropriate qualifiers negatable.
         V03-005 HH0004
                                     Hai Huang
                                                                 09-Mar-1984
                   Add /CLUSTER qualifier.
         V03-004 WMC0001
                                     Wayne Cardoza
                                                                 16-Jan-1984
                   Remove all journaling keywords.
         V03-003 DAS0001
                                     David Solomon
                                                                 29-Nov-1983
                   Add RECORD_SIZE keyword for /JOURNAL qualifier.
         V03-002 MCN0138
                                     Maria del C. Nasr
                                                                 12-Jul-1983
                   Make changes for new CLI interface. Take out prefix clause, which is no longer needed. Add disallow clauses
                   for qualifiers that cannot go together.
         V03-001 MMD0056 Meg Dumont 28-Mar-1983 Changed /OVERRIDE to inc OWNER_IDENTIFIER, added /AUTO and /INIT
define type cache_options
         keyword extent,
keyword file id,
keyword limit,
                                     value(required,type=$number),negatable
                                     value(required, type=$number), negatable
                                     value(required_type=$number)
         keyword quota,
                                     value(required, type=$number), negatable
         keyword writethrough
define type datacheck_options
         keyword read
         keyword write
define type initialize_options
         keyword all
         keyword continuation
!**JNL** define type journal options
!**JNL** keyword newfile
! ** JNL * *
                   keyword size,
                                               value(required,type=$number)
                                               value(required, type=$number)
! ** JNL **
                   keyword extension,
                  keyword quota,
keyword RECORD_SIZE,
! ** JNL **
                                               value(required, type=$number)
! ** JNL **
                                               value(required, type=$number)
define type mount_overrides
         keyword accessibility
         keyword expiration keyword identification, syntax=mount_wo_label
         keyword setid
         keyword lock
         keyword owner_identifier
```

```
define type protection
            keyword system.value
            keyword group, value
            keyword owner value
            keyword world value
define syntax mount_wo_label
           parameter pl,prompt='Device',value(required,list,type=$device),label=devices parameter p2.prompt='Label',value(list),label=volumes parameter p3.prompt='Log name',value(type=$outlog),label=lognames disallow (<mount>foreign or <mount>nolabel) and (<mount>accessed or
                                                                                    <mount>automatic or
                                                                                    <mount>bind or
                                                                                    <mount>cache or
                                                                                    <mount>extension or
                                                                                    <mount>hdr3 or
                                                                                    <mount>initialize or
                                                                                    <mount>label or
                                                                                    <mount>processor or
                                                                                    <mount>quota or
                                                                                    <mount>rebuild or
                                                                                    <mount>windows)
            disallow (<mount>group or <mount>system) and <mount>share
            disallow <mount>system and <mount>group
define verb mount
            image vmount
           parameter pi,prompt='Device',value(required, list, type=$device), label=devices parameter p2,prompt='Label',value(required, list), label=volumes parameter p3,prompt='Log name',value(type=$outlog), label=lognames qualifier accessed, value(required, type=$number)
            qualifier assist
                                               default
            qualifier automatic
                                               default
            qualifier bind,
                                               value(required)
            qualifier blocksize.
                                               value(required,type=$number)
            qualifier cache,
                                               value(required, list, type=cache_options)
            qualifier cluster
            qualifier comment,
                                                value(required)
                                               value(list.type=datacheck_options)
value(required,type=$number)
            qualifier data_check,
            qualifier density,
            qualifier extension,
                                                value(required, type=$number)
            qualifier foreign.
                                               syntax=mount_wo_label,nonnegatable
           qualifier group
qualifier hdr3,
qualifier initialize
                                                default
                                               value(required,type=initialize_options)
! ** JNL **
                       qualifier journal
                                                           value(list.type=journal_options)
  Due to some constraints in DCL and CLI parsing, the NOLABEL qualifier must be defined explicitly in this CLD, and cannot be specified as the negation of LABEL. In that way we can use a different syntax for each one, and also take advantage of the disallow clause.
            qualifier label.
                                                default_nonnegatable
            qualifier nolabel,
                                               nonnegatable, syntax=mount_wo_label
            qualifier message
                                                default
```

The following qualifiers have been commented out, since they were never implemented. They are not being coded with the new CLI interface, but are included here for historical purposes.

0046 AH-BT13A-SE

DIGITAL EQUIPMENT CORPORATION CONFIDENTIAL AND PROPRIETARY

